

# 11 Printing

---

## In this chapter, you will learn how to

- ✓ Add headers and footers to printed pages.
  - ✓ Prepare worksheets for printing.
  - ✓ Print worksheets.
  - ✓ Print parts of worksheets.
  - ✓ Print charts.
- 


Microsoft Excel 2010 gives you a wide range of tools with which to create and manipulate your data. By using filters, by sorting, and by creating PivotTables and charts, you can change your worksheets so that they convey the greatest possible amount of information. After you configure your worksheet so that it shows your data to best advantage, you can print your Excel documents to use in a presentation or include in a report. You can choose to print all or part of any of your worksheets, change how your data and charts appear on the printed page, and even suppress any error messages that might appear in your worksheets.

In this chapter, you'll learn how to prepare your worksheets for printing, print all or part of a worksheet, print charts, and add headers and footers to your worksheets.

**Practice Files** Before you can complete the exercises in this chapter, you need to copy the book's practice files to your computer. The practice files you'll use to complete the exercises in this chapter are in the Chapter11 practice file folder. A complete list of practice files is provided in "Using the Practice Files" at the beginning of this book.

## Adding Headers and Footers to Printed Pages

If you want to ensure that the same information appears at the top or bottom of every printed page, you can do so by using headers or footers. A *header* is a section that appears at the top of every printed page; a *footer* is a section that appears at the bottom of every printed page. To create a header or footer in Excel, you display the Insert tab and then, in the Text group, click Header & Footer to display the Header & Footer Tools Design contextual tab.



**Troubleshooting** The appearance of buttons and groups on the ribbon changes depending on the width of the program window. For information about changing the appearance of the ribbon to match our screen images, see “Modifying the Display of the Ribbon” at the beginning of this book.


When you display your workbook’s headers and footers, Excel displays the workbook in Page Layout view. Page Layout view shows you exactly how your workbook will look when printed, while still enabling you to edit your file, a capability not provided by Print Preview. You can also switch to Page Layout view by displaying the View tab and then, in the Workbook Views group, clicking Page Layout.

**See Also** For information about editing your workbook in Print Preview mode, see the “Previewing Worksheets Before Printing” section later in this chapter.

Excel divides its headers and footers into left, middle, and right sections. When you point to an editable header or footer section, Excel highlights the section to indicate that clicking the left mouse button will open that header or footer section for editing.

**Tip** If you have a chart selected when you click the Header & Footer button on the Insert tab, Excel displays the Header/Footer page of the Page Setup dialog box instead of opening a header or footer section for editing.

When you click a header or footer section, Excel displays the Design contextual tab on the ribbon. The Design contextual tab contains several standard headers and footers, such as page numbers by themselves or followed by the name of the workbook. To add an Auto Header to your workbook, display the Design contextual tab and then, in the Header & Footer group, click Header. Then click the header you want to apply. The list of headers that appears will vary depending on the properties and contents of your worksheet and workbook.



You can also create custom headers by typing your own text or by using the commands in the Header & Footer Elements group to insert a date, time, worksheet name, or page number. You can also add a graphic, such as a company logo, to a worksheet. By adding graphics, you can identify the worksheet as referring to your company and help reinforce your company's identity if you include the worksheet in a printed report distributed outside your company. After you insert a graphic into a header or footer, the Format Picture button in the Header & Footer Elements group will become available. Clicking that button opens a dialog box with tools for editing your graphic.

In this exercise, you'll create a custom header for a workbook. You'll add a graphic to the footer and then edit the graphic by using the Format Picture dialog box.




**SET UP** You need the *RevenueByCustomer\_start* workbook and the *ConsolidatedMessenger* image located in your Chapter11 practice file folder to complete this exercise. Start Excel, open the *RevenueByCustomer\_start* workbook, and save it as *RevenueByCustomer*. Then follow the steps.



1. On the **Insert** tab, in the **Text** group, click **Header & Footer**.

Excel displays your workbook in Page Layout view.



2. In the middle header section, type **Q1 2010**, and then press Enter.
3. On the **Design** contextual tab, in the **Header & Footer Elements** group, click **File Name**.




Excel adds the `&[File]` code to the header.

4. To the right of the `&[File]` code, type a comma, and then press the Spacebar.

5. On the **Design** contextual tab, in the **Header & Footer Elements** group, click **Current Date**.



Excel changes the contents of the middle header section to `&[File], &[Date]`.



6. Press Tab.
- Excel highlights the right header section; the workbook name and current date appear in the middle header section.

7. On the **Design** contextual tab, in the **Navigation** group, click **Go to Footer**.



Excel highlights the right footer section.

8. Click the middle footer section.



9. On the **Design** contextual tab, in the **Header & Footer Elements** group, click **Picture**.

The Insert Picture dialog box opens.

10. Navigate to the **Chapter11** folder, and then double-click **ConsolidatedMessenger.png**.


The code `&[Picture]` appears in the middle footer section.

11. Click any worksheet cell above the footer.

Excel displays the worksheet as it will be printed.

12. Click the image in the footer and then, on the **Design** contextual tab, click **Format Picture**.

The Format Picture dialog box opens.



13. Click the **Size** tab if the **Size** page is not already displayed.

14. In the **Scale** area of the dialog box, in the **Height** field, type **80%**, and then press Enter.

The Format Picture dialog box closes.


15. Click any worksheet cell above the footer.

Excel displays the newly formatted picture.

**✖ CLEAN UP** Save the RevenueByCustomer workbook, and then close it.

## Preparing Worksheets for Printing


When you are ready to print your workbook, you can change the workbook's properties to ensure that your worksheets display all your information and that printing is centered on the page. In Excel, all of these printing functions are gathered together in one place: the Backstage view. To preview your workbook in the Backstage view, click the File tab and then click Print.



**Keyboard Shortcut** Press **Ctrl+P** to preview your worksheet in the Backstage view.

**See Also** For more information about keyboard shortcuts, see “Keyboard Shortcuts” at the end of this book.

Excel comes with three margin settings: Normal, Wide, and Narrow. Excel applies the Normal setting by default, but you can select any of the three options by displaying the workbook in the Backstage view and then, in the Settings area, clicking the Margins button and clicking the desired setting. If you want finer control over your margins, click the Margins button and then Custom Margins to display the Margins page of the Page Setup dialog box.



If you want to display a worksheet's margins while you have its workbook open in the Backstage view, click the Show Margins button near the bottom-right corner of the Backstage view window.



The screenshot shows the Microsoft Excel interface with the Backstage view open. The 'Print' section is active, showing a printer icon, a 'Print' button, and a 'Copies' dropdown set to 1. Below this, the 'Printer' section shows 'Xerox Phaser 6250DP PS' as the selected printer. The 'Settings' section includes options for 'Print Active Sheets', 'Print One Sided', 'Collated', 'Portrait Orientation', 'Letter' paper size, 'Normal Margins', and 'No Scaling'. The 'Page Setup' section is partially visible at the bottom.

Center	Year	Quarter	Revenue
Northwest	2006	1	1535587
Atla m.c	2006	1	2215453.2
Southwest	2006	1	2590008
North Centra l	2006	1	2590021
Midwest	2006	1	22199482
Southwest	2006	1	1779357
Mounta in West	2006	1	22271116
Northwest	2006	1	2530485
Centra l	2006	1	2565599
Northwest	2006	2	1952756
Atla m.c	2006	2	2074526
Southwest	2006	2	2428995
North Centra l	2006	2	2837668
Midwest	2006	2	15103149
Southwest	2006	2	2428995
Mounta in West	2006	2	2541129
Northwest	2006	2	2858162
Centra l	2006	2	16911918
Northwest	2006	3	1925465
Atla m.c	2006	3	1655220
Southwest	2006	3	16909618
North Centra l	2006	3	2179430
Midwest	2006	3	2106400
Southwest	2006	3	16718115
Mounta in West	2006	3	2082505
Northwest	2006	3	2065161
Centra l	2006	3	2186780
Northwest	2006	4	1703272
Atla m.c	2006	4	1810729
Southwest	2006	4	22419129
North Centra l	2006	4	2618286
Midwest	2006	4	17068424
Southwest	2006	4	2470293
Mounta in West	2006	4	2123621
Northwest	2006	4	2975869
Centra l	2006	4	16111547
Northwest	2007	1	26238950
Atla m.c	2007	1	2292563
Southwest	2007	1	1655392
North Centra l	2007	1	2218905
Midwest	2007	1	16946211
Southwest	2007	1	1620448
Mounta in West	2007	1	2221180
Northwest	2007	1	27157426
Centra l	2007	1	2460911

You can drag each margin line to change the corresponding margin's position, increasing or decreasing the amount of space allocated to each worksheet section. Do bear in mind that increasing the size of the header or footer reduces the size of the worksheet body, meaning that fewer rows can be printed on a page.

Another issue with printing worksheets is that the data in worksheets tends to be wider horizontally than a standard sheet of paper. You can use the commands in the Backstage view to change the alignment of the rows and columns on the page. When the columns parallel the long edge of a piece of paper, the page is laid out in portrait mode; when the columns parallel the short edge of a piece of paper, it is in landscape mode.

Changing between portrait and landscape mode can result in a better fit, but you might find that not all of your data will fit on a single printed page. This is where the options available on the Scaling button in the Backstage view come to the rescue. With the Scaling button's options, you can perform three tasks: reduce the size of the worksheet's contents until the worksheet can be printed on a single page, reduce the size of the worksheet's contents until all of the worksheet's columns fit on a single page, or reduce the size of the worksheet's contents until all of the worksheet's rows fit on a single page. You can make the same changes (and more) by using the controls in the Page Setup dialog box. To display the Page Setup dialog box, click the Page Layout tab, and then click the Page Setup dialog box launcher.

## Previewing Worksheets Before Printing


You can view your worksheet as it will be printed by clicking the File tab and then clicking Print in the left pane. When you do, Excel displays the active worksheet in the Backstage view, which includes a preview of the printed worksheet.

When Excel displays your worksheet in the Backstage view, it shows the active worksheet as it will be printed with its current settings. At the bottom of the Backstage view, Excel indicates how many pages the worksheet will require when printed and the number of the page you are viewing.

**Tip** When you display a workbook in the Backstage view, you can see the next printed page by pressing the Page Down key; to move to the previous page, press the Page Up key. You can also use the Previous and Next arrows at the bottom of the Backstage view, type a page number in the Current Page box, or scroll through the pages by using the vertical scroll bar at the right edge of the Backstage view.

## Changing Page Breaks in a Worksheet

Another way to affect how your worksheet will appear on the printed page is to change where Excel assigns its page breaks. A page break is the point at which Excel prints all subsequent data on a new sheet of paper. You can make these changes indirectly by modifying a worksheet's margins, but you can do so directly by displaying your document in Page Break Preview mode. To display your worksheet in Page Break Preview mode, on the View tab, in the Workbook Views group, click Page Break Preview.



The blue lines in the window represent the page breaks. If you want to set a page break manually, you can do so by displaying your worksheet in Page Break Preview mode, right-clicking the row header of the row below where you want the new page to start, and clicking Insert Page Break. In other words, if you right-click the row header of row 15 and click Insert Page Break, row 14 will be the last row on the first printed page, and row 15 will be the first row on the second printed page. The same technique applies to columns: If you right-click the column H column header and click Insert Page Break, column G will be the last column on the first printed page, and column H will be the first column on the second printed page.


You can also add page breaks without displaying your workbook in Page Break Preview mode. To add a page break while your workbook is open in Normal view, click a row or column header and then, on the Page Layout tab, in the Page Setup area, click Breaks, and then click Insert Page Break. Items in the Breaks list also enable you to delete a page break or to reset all of the page breaks in your worksheets.

**Important** Be sure to click a row header or column header when you want to insert a single page break. If you view a workbook in Page Break Preview mode, right-click a cell within the body of a worksheet, and then click Insert Page Break, Excel creates both a vertical page break to the left of the selected cell and a horizontal page break above the selected cell.


To move a page break, drag the line representing the break to its new position. Excel will change the worksheet's properties so that the area you defined will be printed on a single page.

## Changing the Page Printing Order for Worksheets


When you view a document in Page Break Preview mode, Excel indicates the order in which the pages will be printed with light gray words on the worksheet pages. (These indicators appear only in Page Break Preview mode; they don't show up when the document is printed.) You can change the order in which the pages are printed by displaying the Page Layout tab, clicking the Page Setup dialog box launcher, and displaying the Sheet page of the Page Setup dialog box.



In the Page Order area, selecting the Over, Then Down option changes the order in which the worksheets will be printed from the default Down, Then Over. You might want to change the printing order to keep certain information together on consecutive printed pages. For example, suppose you have a worksheet that is designed to hold hourly package pickup information; the columns represent hours of the day, and the rows represent days of the month. If you want to print out consecutive days for each hour, you use Down, Then Over. In a typical configuration, pages 1 and 2 would enable you to see the 5:00 A.M. to 11:00 A.M. pickups for the months of January and February, pages 3 and 4 would enable you to see the 12:00 P.M. to 5:00 P.M. pickups for those months, and so on.



Changing the print order to Over, Then Down for the previous example could print consecutive hours for each day. Pages 1 and 2 would enable you to see the 5:00 A.M. to 5:00 P.M. pickups for January, and pages 3 and 4 would enable you to see the same pickups for February.



In this exercise, you'll preview a worksheet before printing, change a worksheet's margins, change a worksheet's orientation, reduce a worksheet's size, add a page break, and change the page printing order.



**SET UP** You need the **PickupsByHour\_start** workbook located in your **Chapter11** practice file folder to complete this exercise. Open the **PickupsByHour\_start** workbook, and save it as **PickupsByHour**. Then follow the steps.

1. While displaying the **JanFeb** worksheet, click the **File** tab and then click **Print**.  
The workbook appears in the Backstage view.
2. In the Backstage view, click the **Orientation** button, and then click **Landscape Orientation**.  
Excel reorients the worksheet.

- In the Backstage view, click the **Scaling** button, and then click **Custom Scaling Options**.

The Page page of the Page Setup dialog box opens.

- In the **Adjust to** field, type **80%**, and then press Enter.

Excel resizes your worksheet.

- On the ribbon, click the **Page Layout** tab.


Excel displays the JanFeb worksheet and the Page Layout tab.

- Click the row header for row **38**.

Excel highlights row 38.

- On the **Page Layout** tab, in the **Page Setup** group, click **Breaks**, and then click **Insert Page Break**.

Excel sets a horizontal page break above row 38.




The screenshot shows the Microsoft Excel interface with the Page Layout ribbon active. The Breaks button in the Page Setup group is highlighted. The worksheet below displays a data table with a horizontal page break inserted above row 38.

	A	B	C	D	E	F	G	H	I	J	K	L	M	N	O
26			22	1577	1235	1742	1089	2203	2143	1073	1795	1960	1874	1312	1332
27			23	1987	1349	2170	1728	2426	1015	1227	1762	2352	1383	2144	1583
28			24	1868	2459	1380	1390	2270	1336	1886	1541	1774	1911	2079	2269
29			25	1058	1541	1753	1740	2360	2308	2167	1131	1146	1966	2120	2038
30			26	2016	2412	1128	1477	1184	2104	1513	1222	1484	1385	2271	1842
31			27	1640	2180	1904	1048	1531	1541	1858	1744	1605	1280	1937	1013
32			28	2363	1340	2113	1350	1814	2358	1613	1519	1938	1665	1104	1065
33			29	2398	1324	1572	2264	1335	2002	1495	1423	2190	2170	2282	1920
34			30	2225	1178	1633	1148	1640	1872	1581	1431	2024	1423	1972	1674
35			31	1726	1794	2020	1777	1016	1405	1845	2108	1597	1846	1737	2024
36															
37															
38															
39															
40															
41															
42															
43															
44															
45															
46															
47															
48															
49															
50															
51															

Below the data table, a horizontal page break is shown above row 38. The worksheet title is 'February'.

- On the tab bar, click the **MarJun** sheet tab.

The MarJun worksheet appears.



- On the **Page Layout** tab, in the **Page Setup** group, click **Margins**, and then click **Wide**.

Excel applies wide margins to the worksheet.

- On the **Page Layout** tab, click the **Page Setup** dialog box launcher.

The Page Setup dialog box opens.

- If necessary, click the **Sheet** tab.

The Sheet page is displayed.

- In the **Page order** area, click **Over, then down**.

- Click **OK**.

- If desired, click the **File** tab, point to **Print**, and then click the **Print** button.


Excel prints your worksheet.

**✖ CLEAN UP** Save the **PickupsByHour** workbook, and then close it.

## Printing Worksheets

When you're ready to print a worksheet, all you have to do is click the File tab, click Print, and then click the Print button. If you want a little more say in how Excel prints your worksheet, you can use the commands on the Print page of the Backstage view to determine how Excel prints your worksheet. For example, you can choose the printer to which you want to send this job, print multiple copies of the worksheet, and select whether the copies are collated (all pages of a document are printed together) or not (multiple copies of the same page are printed together).





If you want to print more than one worksheet from the active workbook, but not every worksheet in the workbook, you can select the worksheets to print from the tab bar. To select the worksheets to print, hold down the Ctrl key while you click the sheet tabs of the worksheets you want to print. Then click the File tab, click Print, and click the Print button.

**Tip** The worksheets you select for printing do not need to be next to one another in the workbook.

One helpful option on the Sheet page of the Page Setup dialog box is the Cell Errors As box, which enables you to select how Excel will print any errors in your worksheet. You can print an error as it normally appears in the worksheet, print a blank cell in place of the error, or choose one of two other indicators that are not standard error messages.


After you prepare your workbook for printing, you can specify which elements to print by displaying the Print page of the Backstage view and then clicking the Print What button, which displays Print Active Sheets by default. To print the entire worksheet, verify that the Print What button displays Print Active Sheets, and then click the Print button. To print every worksheet in the active workbook, click the Print What button, click the Print Entire Workbook option, and then click the Print button.

In this exercise, you'll print nonadjacent worksheets in your workbook and suppress errors in the printed worksheet.



**SET UP** You need the *SummaryByCustomer\_start* workbook located in your Chapter11 practice file folder to complete this exercise. Open the *SummaryByCustomer\_start* workbook, and save it as *SummaryByCustomer*. Then follow the steps.

1. If necessary, display the **Summary** worksheet.
2. On the **Page Layout** tab, click the **Page Setup** dialog box launcher.  
The Page Setup dialog box opens.
3. Click the **Sheet** tab.  
The Sheet page is displayed.



4. In the **Cell errors as** list, click **<blank>**.
5. Click **OK**.
6. Hold down the Ctrl key and then, on the tab bar, click the **Northwind** sheet tab.  
Excel selects the Summary and Northwind worksheets.
7. Click the **File** tab, and then click **Print**.  
The Print page of the Backstage view is displayed.
8. In the **Settings** area, verify that the **Print Active Sheets** option is selected.
9. Click any ribbon tab to cancel printing, or click the **Print** button if you want to print the worksheets.

**✘ CLEAN UP** Save the SummaryByCustomer workbook, and then close it.

## Printing Parts of Worksheets


Excel gives you a great deal of control over what your worksheets look like when you print them, but you also have a lot of control over which parts of your worksheets will be printed. For example, you can use the commands available on the Print page of the Backstage view to choose which pages of a multipage worksheet you want to print.

In the Settings area of the Print page of the Backstage view, you can fill in the page numbers you want to print in the Pages From and To boxes.

**Tip** You can also use the Page Break Preview window to determine which pages to print, and if the pages aren't in an order you like, you can use the commands on the Sheet page of the Page Setup dialog box to change the order in which they will be printed.

Another way you can modify how a worksheet will be printed is to have Excel fit the entire worksheet on a specified number of pages. For example, you can have Excel resize a worksheet so that it will fit on a single printed page. Fitting a worksheet onto a single page is a handy tool when you need to add a sales or other summary to a report and don't want to spread important information across more than one page.


To have Excel fit a worksheet on a set number of pages, display the Page Layout tab and use the controls in the Scale To Fit group. In the Width and Height lists, you can select how many pages wide or tall you want your printout to be.



If you want to print a portion of a worksheet instead of the entire worksheet, you can define the area or areas you want to have printed. To identify the area of the worksheet you want to print, select the cells with the data you want to print and, on the Page Layout tab, in the Page Setup group, click Print Area and then click Set Print Area. Excel marks the area with a dotted line around the border of the selected cells and prints only the cells you selected. To remove the selection, click Print Area, and then click Clear Print Area.

**Tip** You can include noncontiguous groups of cells in the area to be printed by holding down the Ctrl key as you select the cells.

After you define a print area, you can use the Page Setup dialog box to position the print area on the page. Specifically, you can have Excel center the print area on the page by selecting the Horizontally and Vertically check boxes in the Center On Page area of the Margins page.



If the contents of a worksheet will take up more than one printed page, you can have Excel repeat one or more rows at the top of the page or columns at the left of the page. For example, if you want to print a lengthy worksheet containing the mailing addresses of customers signed up to receive your company's monthly newsletter, you could repeat the column headings Name, Address, City, and so forth at the top of the page. To repeat rows at the top of each printed page, on the Page Layout tab, in the Page Setup group, click Print Titles. Excel will display the Sheet page of the Page Setup dialog box.


On the Sheet page of the Page Setup dialog box, you can use the commands in the Print Titles area to select the rows or columns to repeat. To choose rows to repeat at the top of the page, click the Collapse Dialog button next to the Rows To Repeat At Top box, select the rows, and then click the Expand Dialog button. The rows you selected appear in the Rows To Repeat At Top box.

Similarly, to have a set of columns appear at the left of every printed page, click the Collapse Dialog button next to the Columns To Repeat At Left box, select the columns, and then click the Expand Dialog button. When you're done, click OK to accept the settings.

In this exercise, you'll select certain pages of a worksheet to print, have Excel fit your printed worksheet on a set number of pages, define a multi-region print area, center the printed material on the page, and repeat columns at the left edge of each printed page.



**SET UP** You need the *HourlyPickups\_start* workbook located in your Chapter11 practice file folder to complete this exercise. Open the *HourlyPickups\_start* workbook, and save it as *HourlyPickups*. Then follow the steps.



1. On the **Page Layout** tab, in the **Page Setup** group, click **Print Titles**.

The Page Setup dialog box opens, displaying the Sheet page.

2. At the right edge of the **Columns to repeat at left** field, click the **Collapse Dialog** button.

The dialog box collapses.

3. Select the column header of column **A**, and drag to select the column header of column **B**, too.

The reference  $\$A:\$B$  appears in the Columns To Repeat At Left field.

4. At the right edge of the **Columns to repeat at left** field, click the **Expand Dialog** button.

The dialog box expands.

5. Click **Print Preview**.

Excel displays your worksheet in the Backstage view, which includes a preview of how your worksheet will appear when printed.

The screenshot shows the Microsoft Excel Print Preview interface. The Print dialog box is open, showing the following settings:

- Print**: Copies: 1
- Printer**: Send To OneNote 2010 (Ready)
- Settings**:
  - Print Active Sheets: Only print the active sheets
  - Pages: 1 to 31
  - Collated: 1,2,3 1,2,3
  - Portrait Orientation: 8.5" x 11"
  - Letter: 8.5" x 11"
  - Wide Margins: Left: 1" Right: 1"
  - No Scaling: Print sheets at their actual size

The worksheet preview shows a table for January with the following data:

Day	Hour					
	5:00 AM	6:00 AM	7:00 AM	8:00 AM	9:00 AM	10:00 AM
1	2417	1959	1544	2428	1924	1502
2	1128	1109	1354	1115	2277	1472
3	1228	1250	1692	1728	1892	1710
4	2265	2669	1644	1735	1138	1592
5	1896	1651	1651	1138	1659	2275
6	1224	1536	2248	1208	2109	2282
7	1608	1825	1851	1077	2259	2091
8	1808	2514	1451	1283	2245	1286
9	2275	2560	1392	1511	1942	1609
10	1539	2591	1729	1028	2276	1044
11	1599	1069	1487	1155	2634	2481
12	1773	1782	1224	2426	2638	1514
13	2418	1511	1616	2488	1469	1703
14	1512	2519	2259	1065	1164	2115
15	1003	1283	1874	1512	1228	1963
16	2207	1864	2383	1128	2125	1186
17	1016	2600	1029	1028	1107	2178
18	1704	2261	2166	1996	1650	1899
19	1604	2424	1759	2222	1088	1122
20	2235	2574	1123	2277	1400	2488
21	1388	2521	1171	1884	2292	2467
22	1577	1225	1742	1108	2235	2142
23	1687	1549	2170	1728	2638	1045
24	1898	2659	1380	1390	2270	1396
25	1358	1541	1753	1740	2590	2208
26	2019	2412	1128	1477	1184	2104
27	1640	2680	1904	1048	1531	1541
28	2567	1340	2113	1350	1614	2258
29	2508	1524	1572	2264	1335	2002
30	2225	1178	1633	1148	1640	1872
31	1728	1704	2003	1777	1636	1405
	53560	56791	52467	48918	56079	55826

The text "CONSOLIDATEDMessenger" is visible at the bottom of the worksheet preview.

6. Under **Pages** in the **Settings** area, in the **From** field, type **1**; in the **To** field, type **2**.



7. On the ribbon, click the **Page Layout** tab; in the **Scale to Fit** group, click the **Width** arrow and then, in the list that appears, click **1 page**.



8. Click the **Height** arrow and then, in the list that appears, click **2 pages**.

Excel resizes your worksheet so that it will fit on two printed pages. The new scaling and size values appear in the Scale To Fit group on the Page Layout tab.

9. Select the cell range **A1:E8**, hold down the Ctrl key, and then select the cell range **A38:E45**.



10. On the **Page Layout** tab, in the **Page Setup** group, click **Print Area**, and then click **Set Print Area**.


11. Click the **Page Setup** dialog box launcher.

The Page Setup dialog box opens.

12. On the **Margins** page of the dialog box, in the **Center on page** area, select the **Horizontally** and **Vertically** check boxes.

13. Click **Print Preview**.

Excel displays your worksheet in the Backstage view.



14. On the ribbon, click the **Page Layout** tab.  
Excel displays your worksheet in Normal view.
15. In the **Page Setup** group, click **Print Area**, and then click **Clear Print Area**.  
Excel removes the print areas defined for the JanFeb worksheet.

 **CLEAN UP** Save the *HourlyPickups* workbook, and then close it.


## Printing Charts

With charts, which are graphic representations of your Excel data, you can communicate lots of information with a single picture. Depending on your data and the type of chart you make, you can show trends across time, indicate the revenue share for various departments in a company for a month, or project future sales using trendline analysis. After you create a chart, you can print it to include in a report or use in a presentation.

If you embed a chart in a worksheet, however, the chart will probably obscure some of your data unless you move the chart to a second page in the worksheet. That's one way to handle printing a chart or the underlying worksheet, but there are other ways that don't involve changing the layout of your worksheets.

To print a chart, click the chart, click the File tab, and then click Print to display the Print page in the Backstage view. In the Settings area, Print Selected Chart will be the only option available. If you click anywhere on the worksheet outside the chart, the Print What area opens with the Print Active Sheets option selected, meaning that the chart and underlying worksheet are printed as they appear on the screen. When you're ready to print the chart, click the Print button.


In this exercise, you'll print a chart.

 **SET UP** You need the *CorporateRevenue\_start* workbook located in your Chapter11 practice file folder to complete this exercise. Open the *CorporateRevenue\_start* workbook, and save it as *CorporateRevenue*. Then follow the steps.

1. Select the chart.
2. Click the **File** tab, and then click **Print**.

The Print page of the Backstage view is displayed.






3. Verify that the **Print Selected Chart** option is selected, and then click **Print** (or click any tab on the ribbon to exit the Backstage view if you don't want to print the chart).

**✘ CLEAN UP** Close the *CorporateRevenue* workbook. If you're not continuing directly to the next chapter, exit Excel.

## Key Points



- Through the new Backstage view, Excel gives you complete control over how your worksheets appear on the printed page. Don't be afraid to experiment until you find a look you like.
- Displaying a worksheet in the Backstage view enables you to see what your worksheet will look like on paper before you print, which is a useful feature, especially if you're using an expensive color printer.
- You can preview where the page breaks will fall when you print a worksheet, and you can change them if you want.
- Don't forget that you can have Excel avoid printing error codes! You can repeat rows or columns in a printed worksheet.
- If you want to print a chart without printing the rest of the accompanying worksheet, be sure to select the chart before you start the printing procedure.

# Chapter at a Glance




Enable and examine macros, [page 330](#)

Create and modify macros, [page 336](#)



Run macros when a button is clicked, [page 339](#)



Run macros when a workbook is opened, [page 344](#)